

How to Install **Photoshop Presets**




Photoshop

all versions

1. Open Photoshop


Launch Photoshop as you normally would and open any image.



Version 22.1.1 (Latest version January 2021) for Windows & Mac

2. Apply Camera Raw Filter


In the filter menu choose "Camera Raw Filter..."



Version 22.1.1 (Latest version January 2021) for Windows & Mac

3. Camera Raw


This will open the Camera Raw processing window.



Version 22.1.1 (Latest version January 2021) for Windows & Mac

4. Camera Raw Presets


Click on the presets icon inside Camera Raw



Version 22.1.1 (Latest version January 2021) for Windows & Mac

5. Open menu and choose Import


Right click in the presets area on the right to pop open the presets menu and then select "Import Profiles & Presets..."



Version 22.1.1 (Latest version January 2021) for Windows & Mac

6. Select the Preset Files


Select the Zip File or Folder you downloaded and click "Import".



Version 22.1.1 (Latest version January 2021) for Windows & Mac

7. Select a Preset!


The group of presets is now loaded, you can select any of the presets to preview the effect. Once you have found a preset you like click "OK".



Version 22.1.1 (Latest version January 2021) for Windows & Mac

7. Preset is applied!

Undo and repeat, or adjust the preset settings within Camera Raw to get the exact look you want.



Version 22.1.1 (Latest version January 2021) for Windows & Mac

Older versions of Photoshop

Older versions of Photoshop manage presets for photoshop differently , below are the instructions for loading them.

MAC

- 1.** Open the folder “XMP - Camera Raw Presets” that you downloaded and un-zipped. Select all the “.xmp” files and copy (Command-C).
- 2.** Go to the Finder and open a new window (Command-N).
- 3.** Go to the “Go” Menu at the top, hold down “Alt” or “Option” and the “Library” sub-menu should appear. Click on this.
- 4.** Go to “Application Support” -> “Adobe” -> “Camera Raw” -> “Settings”.
- 5.** In the Settings folder, paste the “.xmp” files you had earlier copied (Command-V).

Older versions of Photoshop

Windows 10

1. Go to the folder:

Windows(user)\Application Data\Adobe\Camera Raw\Settings

or

C:\Users-[user name]\AppData\Roaming\Adobe\CameraRaw\Settings

2. Copy the folder with the XMP presets into the “Settings” folder.

Note: Ensure the XMP files are not in a folder which is inside another folder. It should be ...Settings\FOLDER NAME\Preset.xmp files

Restart Photoshop and the presets will be available from the presets menu inside Camera Raw

Older versions of Photoshop

WINDOWS 7

1. Go to the folder:

Documents and Settings \ YOUR USER NAME \
ApplicationData \ Roaming \ Adobe \ CameraRaw \ Settings

2. Copy the folder with the XMP presets into the “Settings” folder.

Note: If you cannot see the "AppData" folder, do the following:

a. Open Folder Options by clicking the Start button
Picture of the Start button, clicking Control Panel,
clicking Appearance and Personalization, and then
clicking Folder Options.

b. Click the View tab.

c. Under Advanced settings, click Show hidden files,
folders, and drives, and then click OK.